

# Account Balance

This feature allows clients to accumulate positive or negative balances on your site. All the transactions that happen on the clients account balance can be viewed on the client side in the client area's **My Account Balance History** feature.

The **negative balance limit** features can be used in conjunction with each other or individually.

To configure the account balance payment type click on the **configure** button next to account balance in the **PAYMENTS > PAYMENT GATEWAYS** admin tool page. Once through making changes click the **save** button.

## Allow Positive Balance

If you allow **positive balances** on your site clients will be able to add "money" to their account and then pay for listing placement, renewals, subscriptions and features on the site. When you allow positive balances within the system the **add to account balance** link appears in the clients area so that clients can add money to their site balance.

## Allow Negative Balance

If you allow **negative balances** on your site clients can accumulate costs on your site and pay for them at a later time. The client can go to the **My Account Balance History** feature in their client area on the client side to view their current negative balance and add money to their account.

## Negative Balance Time Cutoff

You can set a cut off time for clients to "add" to their negative balance before they cutoff in this setting. From the moment of time that the client goes "negative" in balance there is a count of time accumulating. If this time accumulates beyond the time in days set here the client can no longer charge to their account until the negative balance is cleared. Once the client brings their account to \$0 owed this cutoff time resets and the client again has this amount of time again to "add" to their negative balance before they are cutoff again.

## Negative Balance \$ Cutoff

You can also set the maximum negative balance a single client can accumulate before they are no longer able to charge features on the site to their account. Once their negative balance reaches this amount owed they will need to add money to their account before they can add more charges to their account...again until this limit is reached again.

## Minimum Add to Balance

The value you set here is the minimum amount a client must add to their account balance to add to their account balance on the client side. This setting is best used on site's that use credit card gateways to pay for services on their site. All credit card gateways have fees attached to every transaction and depending on those fees there may be a threshold amount the admin wishes to not allow charge amounts below. This is where that is set.

You as the admin can add any amount to their site balance through the admin tool.

From:  
<http://geodesicsolutions.org/wiki/> - Geodesic Solutions Community Wiki

Permanent link:  
[http://geodesicsolutions.org/wiki/admin\\_menu/payments/payment\\_gateways/account\\_balance/start?rev=1227290783](http://geodesicsolutions.org/wiki/admin_menu/payments/payment_gateways/account_balance/start?rev=1227290783)

Last update: **2014/09/25 16:55**

