

Settings

The Security Image Addon gives you a great deal of flexibility with respect to how you want the image itself to be displayed on your site.

Built in or Security Image Provided by Recaptcha.com

You now have a choice of security images that can be used on your website. You can use the built in security image feature that is configured on this page of the admin tool. You can also choose to use the security image feature through the recaptcha.com website. To start using their image you will need to of course make the choice in this admin tool here. You will also then need to sign up for the service through the recaptcha.com website. Once signed up you will need did to fill in the fields necessary within this admin tool with the api key and private key provided by their website.

Security Image Site Settings

secure registration

This setting allows you to display the security image at the bottom of the Registration Page.

secure login

This setting allows you to display the security image on the software's Login Page. Note that if your software edition displays a login box on the front page, that is actually a separate html form than the Login Page. You can apply the security image to your own forms by using the appropriate tag (shown in 'NOTE' below).

secure messaging

This setting allows you to display the security image on the **Contact Seller** and **Tell-a-Friend** forms accessible from the Listing Display Page.

<tip c n> The security image can also be used within custom login forms that you may have applied to your site. If so, then simply insert the following tag within the <form> tags of your form:

```
(!addon.geo_addons.security_image.secure_image!)
```

</tip>

Security Image Settings

image height

This setting allows you to define the height (in pixels) of the security image box.

image width

This setting allows you to define the width (in pixels) of the security image box.

number of characters

This setting allows you to define the number of characters that will be displayed in the security image box.

font size (1-5)

This setting allows you to define the size of the characters that appear in the security image box.

Security Image Debris Settings

blur security image (php 5)

This setting allows you to apply a blur to the characters. Please note that it may only be used if you are running php 5 or later on your server.

distort security image

This setting allows you to apply distortion (skewing) of the security image.

random colors

This setting allows you to apply different colors to the characters, grid, lines, and noise each time the security image is refreshed.

random grid

This setting allows you to apply a set of grid lines to the security image.

random lines

This setting allows you to apply a set of lines to the security image.

random noise

This setting allows you to apply pixel points to the background of the security image.

Advanced Security Image Settings

min ascii value

This setting allows you to

max ascii value

This setting allows you to

number of grid lines

If the **random grid** setting above is in use, you can specify the number of grid lines that will display in the image.

number of lines

If the **random lines** setting above is in use, you can specify the number of lines that will display in the image.

amount of noise

If the **random noise** setting above is in use, you can specify the amount of noise that will display in the image.

distortion amount

If the **distort security image** setting above is in use, you can specify the degree of distortion that will be applied to the contents of the security image.

Last update: 2014/09/25 16:55 admin_menu:addons:security_image:settings:start https://geodesicsolutions.org/wiki/admin_menu/addons/security_image/settings/start?rev=1287683976

From: <https://geodesicsolutions.org/wiki/> - **Geodesic Solutions Community Wiki**

Permanent link: https://geodesicsolutions.org/wiki/admin_menu/addons/security_image/settings/start?rev=1287683976

Last update: **2014/09/25 16:55**

